

# FAQ N510 Maxwell C Support

## Introduction

The [Maxwell C](#) is fully supported behind the N510 from Software 247 or higher. If the software is older then it will operate in GAP modes with limited functionality.

Software 247 is available from mid of June 2018.

[Download](#)

## Firmware update

1. Upgrade your N510 to software 247 or higher.
2. After the upgrade, the Maxwell C will be fully supported.

## Patch

If you would like to use the Maxwell C with older software, you can download this patch and install this on your N510.

1. Download the Patch file and put this on your PC.
2. Open the web-interface of the N510, go to: Settings - Management - Save & Restore.
3. Restore this Patch file.
4. Device will reboot.
5. After the reboot the Maxwell C will be fully supported.