Maxwell 10 Build 2.10.27

Release Notes

Release Date:

19.02.2019

Version:

2.10.27

Improvements

- Implemetation of all availailable security patches for 2018
- Support of Cyrillc characters
- Handling of *.wav files
 Cascaded provisioning files
- · Editing contacts from call list and sharing via gmail
- AndroidStudio Support
- PBX interoperability

Bugfixes

Multiple fixes implemented

Information

Due to technical design, wireless LAN and Bluetooth Audio should not be used simultaneously



Software versions	
Android	5.1.1
DVF9919	03.641a
Build number	80_1_2.10.27

Firmware update



Important

Due to the fact, that Android-5.1 requires a lot of more memory than older Android versions we recommend to insert an external SD-card, or plug in an USB-stick with minimum 2GB free memory space, at least during the upgrade phase!

There are 3 options to upgrade.

Option 1: Two step Method using an SD-card or USB-memory-stick.

1. Plug in an SD-card or USB-stick with at least 2GB free memory (or enter an external SD card). Then start the Maxwell-10 WEB-UI (klick on the Web Server Address - shown in the Maxwell 10 under "Settings=>WebUI - log in (Standard Password is "admin") and follow exactly the following 3 steps:

2. In the web-interface go to: System - Firmware Update page and check if the Data server field is (default) profile.gigaset.net/device

Update firmware profile.gigaset.net/device Data server ..set custom url here


- 3. Press "Save"
- 4. Press "Update firmware"

The update will be done in 2 steps.

- 1. Upgrade to new Jelly Bean software with USB drivers upgrade to support the USB memory extension.
- 2. Upgrade to Lollipop.

Option 2: One step method using external SD-card.

- Enter an external SD-card (or plug in an USB-stick).
 Download the software via the "Download" button on this page.
- 3. Unpack the zip file. You will get a .txt file with the Open Source License text and an encrypted zip file which is your firmware image.
- 4. In the web-interface go to: System Firmware Update page and select the above extracted zip file.



5. Start the upgrade.